

# Configure Shipbridge for Skustack

04/09/2025 12:48 pm CDT


## Overview

Skustack can integrate with [Shipbridge](#), Sellercloud's shipping app, in just a few simple steps. This connection can streamline your warehouse processes further and allows you to utilize thermal printers configured within your Shipbridge installation via your Skustack device.

## Integrate Shipbridge with Skustack


Here's how to configure Shipbridge to work with Skustack:

1. Log into Shipbridge and configure your warehouse [locations and stations](#).
2. Next, navigate to **Menu > Options > Shipping** tab and enable **When using multiple warehouses, deduct inv qty from the proper warehouse (based on location)**. The order will be shipped and inventory will always be deducted from the warehouse location Shipbridge is set to.



The screenshot shows the 'Options' window in Shipbridge, with the 'Shipping' tab selected. The checkbox 'When using multiple warehouses, deduct inv qty from proper warehouse (based on location)' is checked and highlighted with a red box. A red arrow points to this checkbox. Other visible options include 'Reference fields: Use product name instead of order item description', 'Slightly validate addresses with standard changes (ZIP+4, abbreviations)', 'Use company first/last names instead of company name', 'Always recalculate order weight based on product/item weight', 'Recalculate package weight based on order weight', 'Ignore zero-weight products when calculating package and order weight', 'Warn when shipping an order with \$0 declared value', 'Use old package editor code', 'Only update ShipWeight when saving order/product weights', 'Allow batch unshipping', 'Maximum number of orders to batch unship' (75), 'Only batch unship orders that are' (10 days old), 'Calculate order weight based on kit items', 'Calculate per-package weight for multi-package orders', and 'Use per-package dimensions for multi-package orders (loaded from products)'. The bottom of the window has buttons for 'Run Configuration Wizard', 'Find setting...', 'Find Next', 'Apply', 'Save', and 'Cancel'.

3. Open the **Options > General** tab and enable **Only load orders from specific warehouse**. Select the desired warehouse from the dropdown menu or click **From Location**. Orders will only be loaded and shipped from the chosen warehouse location.



4. (Recommended) Enable Shipbridge Admin setting **Only allow shipping of Fully Picked orders**. This will prevent orders from being shipped before they are fully picked.  
The Admin tab settings can only be modified by [Sellercloud support](#). Contact our team to have this setting enabled on your shipping station.

5. Click **Save**.

6. To use an [RTC printer connection type](#), log into your Skustack device and go to **Settings > Shipping** to select the

Shipbridge Installation to integrate with.

